django-maintenance-window Documentation

Release 0.3.3

Jorik Kraaikamp

Contents

1	ljango-maintenance-window	3
	Documentation	3
	.2 Quickstart	
	1.3 Settings	
	1.4 Running Tests	
	1.5 Credits	
2	Installation	5
3	Usage	7
4	Contributing	9
-	4.1 Types of Contributions	-
	1.2 Get Started!	
	4.3 Pull Request Guidelines	
	1.4 Tips	
5	Credits 1	13
	5.1 Development Lead	
	5.2 Contributors	
	Conditioned	
6		15
	5.1 0.2.1 (2017-10-30)	15
	5.2 0.2.0 (2017-10-26)	15
	5.3 0.1.0 (2017-10-26)	15

Contents:

Contents 1

2 Contents

django-maintenance-window

Your project description goes here

1.1 Documentation

The full documentation is at https://django-maintenance-window.readthedocs.io.

1.2 Quickstart

Install django-maintenance-window:

```
pip install django-maintenance-window
```

Add it to your INSTALLED_APPS:

```
INSTALLED_APPS = (
    ...
    'django-solo',
    'django_maintenance_window',
    ...
)
```

Add django-maintenance-window's middleware to the middleware:

or

```
MIDDLEWARE = [
    ...
    'django_maintenance_window.middleware.MaintenanceModeMiddleware',
    ...
]
```

1.3 Settings

- MAINTENANCE_TEMPLATE = 'django_maintenance_window/maintenance.html' Overwrite the template that is used for the maintenance template
- MAINTENANCE_DISPLAY_END_DATE = False If the end date should be displayed at the bottom of the page.
- MAINTENANCE_EXCLUDE_ADMIN_URLS = True This will allow accessing the admin even if maintenance mode is active.
- MAINTENANCE_EXCLUDE_SUPER_USER = False This will allow super users to see the site even if maintenance mode is active.
- MAINTENANCE_EXCLUDE_STAFF_USER = False This will allow staff users to see the site even if maintenance mode is active.

1.4 Running Tests

Does the code actually work?

```
source <YOURVIRTUALENV>/bin/activate
(myenv) $ pip install tox
(myenv) $ tox
```

1.5 Credits

Tools used in rendering this package:

- Cookiecutter
- cookiecutter-djangopackage

Installation

At the command line:

\$ easy_install django-maintenance-window

Or, if you have virtualenvwrapper installed:

\$ mkvirtualenv django-maintenance-window \$ pip install django-maintenance-window

Usage

To use django-maintenance-window in a project, add it to your *INSTALLED_APPS*:

```
INSTALLED_APPS = (
    ...
    'django_maintenance_window.apps.DjangoMaintenanceWindowConfig',
    ...
)
```

Add django-maintenance-window's URL patterns:

```
from django_maintenance_window import urls as django_maintenance_window_urls

urlpatterns = [
    ...
    url(r'^', include(django_maintenance_window_urls)),
    ...
]
```

8 Chapter 3. Usage

Contributing

Contributions are welcome, and they are greatly appreciated! Every little bit helps, and credit will always be given. You can contribute in many ways:

4.1 Types of Contributions

4.1.1 Report Bugs

Report bugs at https://github.com/jostcrow/django-maintenance-window/issues.

If you are reporting a bug, please include:

- Your operating system name and version.
- Any details about your local setup that might be helpful in troubleshooting.
- Detailed steps to reproduce the bug.

4.1.2 Fix Bugs

Look through the GitHub issues for bugs. Anything tagged with "bug" is open to whoever wants to implement it.

4.1.3 Implement Features

Look through the GitHub issues for features. Anything tagged with "feature" is open to whoever wants to implement it.

4.1.4 Write Documentation

django-maintenance-window could always use more documentation, whether as part of the official django-maintenance-window docs, in docstrings, or even on the web in blog posts, articles, and such.

4.1.5 Submit Feedback

The best way to send feedback is to file an issue at https://github.com/jostcrow/django-maintenance-window/issues.

If you are proposing a feature:

- Explain in detail how it would work.
- Keep the scope as narrow as possible, to make it easier to implement.
- Remember that this is a volunteer-driven project, and that contributions are welcome:)

4.2 Get Started!

Ready to contribute? Here's how to set up django-maintenance-window for local development.

- 1. Fork the *django-maintenance-window* repo on GitHub.
- 2. Clone your fork locally:

```
$ git clone git@github.com:your_name_here/django-maintenance-window.git
```

3. Install your local copy into a virtualenv. Assuming you have virtualenvwrapper installed, this is how you set up your fork for local development:

```
$ mkvirtualenv django-maintenance-window
$ cd django-maintenance-window/
$ python setup.py develop
```

4. Create a branch for local development:

```
$ git checkout -b name-of-your-bugfix-or-feature
```

Now you can make your changes locally.

5. When you're done making changes, check that your changes pass flake8 and the tests, including testing other Python versions with tox:

```
$ flake8 django_maintenance_window tests
$ python setup.py test
$ tox
```

To get flake8 and tox, just pip install them into your virtualenv.

6. Commit your changes and push your branch to GitHub:

```
$ git add .
$ git commit -m "Your detailed description of your changes."
$ git push origin name-of-your-bugfix-or-feature
```

7. Submit a pull request through the GitHub website.

4.3 Pull Request Guidelines

Before you submit a pull request, check that it meets these guidelines:

- 1. The pull request should include tests.
- 2. If the pull request adds functionality, the docs should be updated. Put your new functionality into a function with a docstring, and add the feature to the list in README.rst.
- 3. The pull request should work for Python 2.6, 2.7, and 3.3, and for PyPy. Check https://travis-ci.org/jostcrow/django-maintenance-window/pull_requests and make sure that the tests pass for all supported Python versions.

4.4 Tips

To run a subset of tests:

\$ python -m unittest tests.test_django_maintenance_window

Credits

5.1 Development Lead

• Jorik Kraaikamp <jorik@maykinmedia.nl>

5.2 Contributors

None yet. Why not be the first?

14 Chapter 5. Credits

History

6.1 0.2.1 (2017-10-30)

• Fixed that the admin would give a 500 when you only set the maintenance_from.

6.2 0.2.0 (2017-10-26)

- Now the admin exclude will work with i18n urls.
- MAINTENANCE_EXCLUDE_ADMIN_URLS is now a setting (default=True)
- MAINTENANCE_EXCLUDE_SUPER_USER is now a setting (default=False)
- MAINTENANCE_EXCLUDE_STAFF_USER is now a setting (default=False)

6.3 0.1.0 (2017-10-26)

• First release on PyPI.